

---

# Pacemaker Remote

*Release 2.1.8*

the Pacemaker project contributors

Aug 08, 2024



# CONTENTS

<b>1</b>	<b>Abstract</b>	<b>3</b>
<b>2</b>	<b>Table of Contents</b>	<b>5</b>
2.1	Scaling a Pacemaker Cluster . . . . .	5
2.1.1	Overview . . . . .	5
2.1.2	Terms . . . . .	5
2.1.3	Guest Nodes . . . . .	6
2.1.4	Remote Nodes . . . . .	7
2.1.5	Expanding the Cluster Stack . . . . .	7
2.2	Configuration Explained . . . . .	8
2.2.1	Resource Meta-Attributes for Guest Nodes . . . . .	8
2.2.2	Connection Resources for Remote Nodes . . . . .	9
2.2.3	Environment Variables for Daemon Start-up . . . . .	9
2.2.4	Removing Remote Nodes and Guest Nodes . . . . .	11
2.3	Guest Node Walk-through . . . . .	11
2.3.1	Configure Cluster Nodes . . . . .	11
2.3.2	Configure the KVM guest . . . . .	11
2.3.3	Integrate Guest into Cluster . . . . .	13
2.3.4	Starting Resources on KVM Guest . . . . .	16
2.3.5	Testing Recovery and Fencing . . . . .	17
2.3.6	Accessing Cluster Tools from Guest Node . . . . .	19
2.3.7	Troubleshooting a Remote Connection . . . . .	19
2.4	Remote Node Walk-through . . . . .	20
2.4.1	Configure Cluster Nodes . . . . .	20
2.4.2	Configure Remote Node . . . . .	20
2.4.3	How pcs Configures the Remote . . . . .	22
2.4.4	Starting Resources on Remote Node . . . . .	23
2.4.5	Fencing Remote Nodes . . . . .	23
2.4.6	Accessing Cluster Tools from a Remote Node . . . . .	23
2.4.7	Troubleshooting a Remote Connection . . . . .	23
2.5	Alternative Configurations . . . . .	24
2.5.1	Virtual Machines as Cluster Nodes . . . . .	24
2.5.2	Virtual Machines as Remote Nodes . . . . .	24
2.5.3	Containers as Guest Nodes . . . . .	24
<b>3</b>	<b>Index</b>	<b>27</b>
	<b>Index</b>	<b>29</b>



*Scaling High Availability Clusters*



## ABSTRACT

This document exists as both a reference and deployment guide for the Pacemaker Remote service.

The example commands in this document will use:

- AlmaLinux 9 as the host operating system
- Pacemaker Remote to perform resource management within guest nodes and remote nodes
- KVM for virtualization
- libvirt to manage guest nodes
- Corosync to provide messaging and membership services on cluster nodes
- Pacemaker 2 to perform resource management on cluster nodes
- pcs as the cluster configuration toolset

The concepts are the same for other distributions, virtualization platforms, toolsets, and messaging layers, and should be easily adaptable.





## TABLE OF CONTENTS

### 2.1 Scaling a Pacemaker Cluster

#### 2.1.1 Overview

In a basic Pacemaker high-availability cluster<sup>1</sup> each node runs the full cluster stack of Corosync and all Pacemaker components. This allows great flexibility but limits scalability to around 32 nodes.

To allow for scalability to dozens or even hundreds of nodes, Pacemaker allows nodes not running the full cluster stack to integrate into the cluster and have the cluster manage their resources as if they were a cluster node.

#### 2.1.2 Terms

**cluster node** A node running the full high-availability stack of corosync and all Pacemaker components. Cluster nodes may run cluster resources, run all Pacemaker command-line tools (`crm_mon`, `crm_resource` and so on), execute fencing actions, count toward cluster quorum, and serve as the cluster's Designated Controller (DC).

**pacemaker-remoted** A small service daemon that allows a host to be used as a Pacemaker node without running the full cluster stack. Nodes running `pacemaker-remoted` may run cluster resources and most command-line tools, but cannot perform other functions of full cluster nodes such as fencing execution, quorum voting, or DC eligibility. The `pacemaker-remoted` daemon is an enhanced version of Pacemaker's local executor daemon (`pacemaker-execd`).

**pacemaker\_remote** The name of the systemd service that manages `pacemaker-remoted`

**Pacemaker Remote** A way to refer to the general technology implementing nodes running `pacemaker-remoted`, including the cluster-side implementation and the communication protocol between them.

**remote node** A physical host running `pacemaker-remoted`. Remote nodes have a special resource that manages communication with the cluster. This is sometimes referred to as the *bare metal* case.

**guest node** A virtual host running `pacemaker-remoted`. Guest nodes differ from remote nodes mainly in that the guest node is itself a resource that the cluster manages.

---

**Note:** *Remote* in this document refers to the node not being a part of the underlying corosync cluster. It has nothing to do with physical proximity. Remote nodes and guest nodes are subject to the same latency

---

<sup>1</sup> See the [https://www.clusterlabs.org/doc/](https://www.clusterlabs.org/doc/Pacemaker_documentation) Pacemaker documentation, especially *Clusters From Scratch* and *Pacemaker Explained*.

requirements as cluster nodes, which means they are typically in the same data center.

---

**Note:** It is important to distinguish the various roles a virtual machine can serve in Pacemaker clusters:

- A virtual machine can run the full cluster stack, in which case it is a cluster node and is not itself managed by the cluster.
  - A virtual machine can be managed by the cluster as a resource, without the cluster having any awareness of the services running inside the virtual machine. The virtual machine is *opaque* to the cluster.
  - A virtual machine can be a cluster resource, and run `pacemaker-remoted` to make it a guest node, allowing the cluster to manage services inside it. The virtual machine is *transparent* to the cluster.
- 

### 2.1.3 Guest Nodes

**“I want a Pacemaker cluster to manage virtual machine resources, but I also want Pacemaker to be able to manage the resources that live within those virtual machines.”**

Without `pacemaker-remoted`, the possibilities for implementing the above use case have significant limitations:

- The cluster stack could be run on the physical hosts only, which loses the ability to monitor resources within the guests.
- A separate cluster could be on the virtual guests, which quickly hits scalability issues.
- The cluster stack could be run on the guests using the same cluster as the physical hosts, which also hits scalability issues and complicates fencing.

With `pacemaker-remoted`:

- The physical hosts are cluster nodes (running the full cluster stack).
- The virtual machines are guest nodes (running `pacemaker-remoted`). Nearly zero configuration is required on the virtual machine.
- The cluster stack on the cluster nodes launches the virtual machines and immediately connects to `pacemaker-remoted` on them, allowing the virtual machines to integrate into the cluster.

The key difference here between the guest nodes and the cluster nodes is that the guest nodes do not run the cluster stack. This means they will never become the DC, initiate fencing actions or participate in quorum voting.

On the other hand, this also means that they are not bound to the scalability limits associated with the cluster stack (no 32-node corosync member limits to deal with). That isn't to say that guest nodes can scale indefinitely, but it is known that guest nodes scale horizontally much further than cluster nodes.

Other than the quorum limitation, these guest nodes behave just like cluster nodes with respect to resource management. The cluster is fully capable of managing and monitoring resources on each guest node. You can build constraints against guest nodes, put them in standby, or do whatever else you'd expect to be able to do with cluster nodes. They even show up in `crm_mon` output as nodes.

To solidify the concept, below is an example that is very similar to an actual deployment that we tested in a developer environment to verify guest node scalability:

- 16 cluster nodes running the full Corosync + Pacemaker stack
- 64 Pacemaker-managed virtual machine resources running `pacemaker-remoted` configured as guest nodes

- 64 Pacemaker-managed webserver and database resources configured to run on the 64 guest nodes

With this deployment, you would have 64 webserver and databases running on 64 virtual machines on 16 hardware nodes, all of which are managed and monitored by the same Pacemaker deployment. It is known that `pacemaker-remoted` can scale to these lengths and possibly much further depending on the specific scenario.

## 2.1.4 Remote Nodes

**“I want my traditional high-availability cluster to scale beyond the limits imposed by the corosync messaging layer.”**

Ultimately, the primary advantage of remote nodes over cluster nodes is scalability. There are likely some other use cases related to geographically distributed HA clusters that remote nodes may serve a purpose in, but those use cases are not well understood at this point.


Like guest nodes, remote nodes will never become the DC, initiate fencing actions or participate in quorum voting.

That is not to say, however, that fencing of a remote node works any differently than that of a cluster node. The Pacemaker scheduler understands how to fence remote nodes. As long as a fencing device exists, the cluster is capable of ensuring remote nodes are fenced in the exact same way as cluster nodes.


## 2.1.5 Expanding the Cluster Stack

With `pacemaker-remoted`, the traditional view of the high-availability stack can be expanded to include a new layer:

### Traditional HA Stack



HA Stack With Guest Nodes



## 2.2 Configuration Explained

The walk-through examples use some of these options, but don't explain exactly what they mean or do. This section is meant to be the go-to resource for all the options available for configuring Pacemaker Remote.

### 2.2.1 Resource Meta-Attributes for Guest Nodes

When configuring a virtual machine as a guest node, the virtual machine is created using one of the usual resource agents for that purpose (for example, `ocf:heartbeat:VirtualDomain` or `ocf:heartbeat:Xen`), with additional meta-attributes.

No restrictions are enforced on what agents may be used to create a guest node, but obviously the agent must create a distinct environment capable of running the `pacemaker_remote` daemon and cluster resources. An additional requirement is that fencing the host running the guest node resource must be sufficient for ensuring the guest node is stopped. This means, for example, that not all hypervisors supported by `VirtualDomain` may be used to create guest nodes; if the guest can survive the hypervisor being fenced, it may not be used as a guest node.

Below are the meta-attributes available to enable a resource as a guest node and define its connection parameters.

Table 1: Meta-attributes for configuring VM resources as guest nodes

Option	Default	Description
remote-node	none	The node name of the guest node this resource defines. This both enables the resource as a guest node and defines the unique name used to identify the guest node. If no other parameters are set, this value will also be assumed as the hostname to use when connecting to <code>pacemaker_remote</code> on the VM. This value <b>must not</b> overlap with any resource or node IDs.
remote-port	3121	The port on the virtual machine that the cluster will use to connect to <code>pacemaker_remote</code> .
remote-addr	'value of remote-node'	The IP address or hostname to use when connecting to <code>pacemaker_remote</code> on the VM.
remote-connect-timeout	60s	How long before a pending guest connection will time out.
remote-allow-migrate	TRUE	The <code>allow-migrate</code> meta-attribute value for the implicit remote connection resource ( <code>ocf:pacemaker:remote</code> ).

## 2.2.2 Connection Resources for Remote Nodes

A remote node is defined by a connection resource. That connection resource has instance attributes that define where the remote node is located on the network and how to communicate with it.

Descriptions of these instance attributes can be retrieved using the following `pcs` command:

```
[root@pcmk-1 ~]# pcs resource describe remote
Assumed agent name 'ocf:pacemaker:remote' (deduced from 'remote')
ocf:pacemaker:remote - Pacemaker Remote connection

Resource options:
  server (unique group: address): Server location to connect to (IP address
                                or resolvable host name)
  port (unique group: address): TCP port at which to contact Pacemaker
                                Remote executor
  reconnect_interval: If this is a positive time interval, the cluster will
                     attempt to reconnect to a remote node after an active
                     connection has been lost at this interval. Otherwise,
                     the cluster will attempt to reconnect immediately
                     (after any fencing needed).
```

When defining a remote node's connection resource, it is common and recommended to name the connection resource the same as the remote node's hostname. By default, if no `server` option is provided, the cluster will attempt to contact the remote node using the resource name as the hostname.

## 2.2.3 Environment Variables for Daemon Start-up

Authentication and encryption of the connection between cluster nodes and nodes running `pacemaker_remote` is achieved using with [TLS-PSK](#) encryption/authentication over TCP (port 3121 by default).

This means that both the cluster node and remote node must share the same private key. By default, this key is placed at `/etc/pacemaker/authkey` on each node.

You can change the default port and/or key location for Pacemaker and `pacemaker_remoted` via environment variables. How these variables are set varies by OS, but usually they are set in the `/etc/sysconfig/pacemaker` or `/etc/default/pacemaker` file.

```
##===# Pacemaker Remote
# Use the contents of this file as the authorization key to use with Pacemaker
# Remote connections. This file must be readable by Pacemaker daemons (that is,
# it must allow read permissions to either the hacluster user or the haclient
# group), and its contents must be identical on all nodes. The default is
# "/etc/pacemaker/authkey".
# PCMK_authkey_location=/etc/pacemaker/authkey

# If the Pacemaker Remote service is run on the local node, it will listen
# for connections on this address. The value may be a resolvable hostname or an
# IPv4 or IPv6 numeric address. When resolving names or using the default
# wildcard address (i.e. listen on all available addresses), IPv6 will be
# preferred if available. When listening on an IPv6 address, IPv4 clients will
# be supported (via IPv4-mapped IPv6 addresses).
# PCMK_remote_address="192.0.2.1"

# Use this TCP port number when connecting to a Pacemaker Remote node. This
# value must be the same on all nodes. The default is "3121".
# PCMK_remote_port=3121

# Use these GnuTLS cipher priorities for TLS connections. See:
#
# https://gnutls.org/manual/html\_node/Priority-Strings.html
#
# Pacemaker will append "+ANON-DH" for remote CIB access (when enabled) and
# "+DHE-PSK:+PSK" for Pacemaker Remote connections, as they are required for
# the respective functionality.
# PCMK_tls_priorities="NORMAL"

# Set bounds on the bit length of the prime number generated for Diffie-Hellman
# parameters needed by TLS connections. The default is not to set any bounds.
#
# If these values are specified, the server (Pacemaker Remote daemon, or CIB
# manager configured to accept remote clients) will use these values to provide
# a floor and/or ceiling for the value recommended by the GnuTLS library. The
# library will only accept a limited number of specific values, which vary by
# library version, so setting these is recommended only when required for
# compatibility with specific client versions.
#
# If PCMK_dh_min_bits is specified, the client (connecting cluster node or
# remote CIB command) will require that the server use a prime of at least this
# size. This is only recommended when the value must be lowered in order for
# the client's GnuTLS library to accept a connection to an older server.
# The client side does not use PCMK_dh_max_bits.
#
# PCMK_dh_min_bits=1024
# PCMK_dh_max_bits=2048
```

## 2.2.4 Removing Remote Nodes and Guest Nodes

If the resource creating a guest node, or the `ocf:pacemaker:remote` resource creating a connection to a remote node, is removed from the configuration, the affected node will continue to show up in output as an offline node.

If you want to get rid of that output, run (replacing `$NODE_NAME` appropriately):

```
# crm_node --force --remove $NODE_NAME
```

**Warning:** Be absolutely sure that there are no references to the node's resource in the configuration before running the above command.

## 2.3 Guest Node Walk-through

**What this tutorial is:** An in-depth walk-through of how to get Pacemaker to manage a KVM guest instance and integrate that guest into the cluster as a guest node.

**What this tutorial is not:** A realistic deployment scenario. The steps shown here are meant to get users familiar with the concept of guest nodes as quickly as possible.

### 2.3.1 Configure Cluster Nodes

This walk-through assumes you already have a Pacemaker cluster configured. For examples, we will use a cluster with two cluster nodes named `pcmk-1` and `pcmk-2`. You can substitute whatever your node names are, for however many nodes you have. If you are not familiar with setting up basic Pacemaker clusters, follow the walk-through in the Clusters From Scratch document before attempting this one.

#### Install Virtualization Software

On each node within your cluster, install `virt-install`, `libvirt`, and `qemu-kvm`. Start and enable `virtnetworkd`.

```
# dnf install -y virt-install libvirt qemu-kvm
# systemctl start virtnetworkd
# systemctl enable virtnetworkd
```

Reboot the host.

**Note:** While KVM is used in this example, any virtualization platform with a Pacemaker resource agent can be used to create a guest node. The resource agent needs only to support usual commands (start, stop, etc.); Pacemaker implements the **remote-node** meta-attribute, independent of the agent.

### 2.3.2 Configure the KVM guest

### Create Guest

Create a KVM guest to use as a guest node. Be sure to configure the guest with a hostname and a static IP address (as an example here, we will use `guest1` and `192.168.122.10`). Here's an example way to create a guest:

- Download an `.iso` file from the AlmaLinux 9 [mirrors list](#) into a directory on your cluster node.
- Run the following command, using your own path for the `location` flag:

```
[root@pcmk-1 ~]# virt-install \  
  --name vm-guest1 \  
  --memory 1536 \  
  --disk path=/var/lib/libvirt/images/vm-guest1.qcow2,size=4 \  
  --vcpus 2 \  
  --os-variant almalinux9 \  
  --network bridge=virbr0 \  
  --graphics none \  
  --console pty,target_type=serial \  
  --location /tmp/AlmaLinux-9-latest-x86_64-dvd.iso \  
  --extra-args 'console=ttyS0,115200n8'
```

---

**Note:** See the Clusters from Scratch document for more details about installing AlmaLinux 9. The above command will perform a text-based installation by default, but feel free to do a graphical installation, which exposes more options.

---

### Configure Firewall on Guest

On each guest, allow cluster-related services through the local firewall. If you're using `firewalld`, run the following commands.

```
[root@guest1 ~]# firewall-cmd --permanent --add-service=high-availability  
success  
[root@guest1 ~]# firewall-cmd --reload  
success
```

---

**Note:** If you are using some other firewall solution besides `firewalld`, simply open the following ports, which can be used by various clustering components: TCP ports 2224, 3121, and 21064.

If you run into any problems during testing, you might want to disable the firewall and SELinux entirely until you have everything working. This may create significant security issues and should not be performed on machines that will be exposed to the outside world, but may be appropriate during development and testing on a protected host.

To disable security measures:

```
[root@guest1 ~]# setenforce 0  
[root@guest1 ~]# sed -i.bak "s/SELINUX=enforcing/SELINUX=permissive/g" \  
  /etc/selinux/config  
[root@guest1 ~]# systemctl mask firewalld.service  
[root@guest1 ~]# systemctl stop firewalld.service
```

---



## Configure /etc/hosts

You will need to add the remote node's hostname (we're using **guest1** in this tutorial) to the cluster nodes' `/etc/hosts` files if you haven't already. This is required unless you have DNS set up in a way where `guest1`'s address can be discovered.

For each guest, execute the following on each cluster node and on the guests, replacing the IP address with the actual IP address of the guest node.

```
# cat << END >> /etc/hosts
192.168.122.10  guest1
END
```

Also add entries for each cluster node to the `/etc/hosts` file on each guest. For example:

```
# cat << END >> /etc/hosts
192.168.122.101  pcmk-1
192.168.122.102  pcmk-2
END
```

## Verify Connectivity

At this point, you should be able to ping and ssh into guests from hosts, and vice versa.

Depending on your installation method, you may have to perform an additional step to make SSH work. The simplest approach is to open the `/etc/ssh/sshd_config` file and set `PermitRootLogin yes`. Then to make the change take effect, run the following command.

```
[root@guest1 ~]# systemctl restart sshd
```

## Configure pacemaker\_remote on Guest Node

Install the `pacemaker_remote` daemon on the guest node. We'll also install the `pacemaker` package. It isn't required for a guest node to run, but it provides the `crm_attribute` tool, which many resource agents use.

```
[root@guest1 ~]# dnf config-manager --set-enabled highavailability
[root@guest1 ~]# dnf install -y pacemaker-remote resource-agents pcs \
  pacemaker
```

## 2.3.3 Integrate Guest into Cluster

Now the fun part, integrating the virtual machine you've just created into the cluster. It is incredibly simple.

### Start the Cluster

On the host, start Pacemaker if it's not already running.

```
# pcs cluster start
```

## Create a VirtualDomain Resource for the Guest VM

For this simple walk-through, we have created the VM and made its disk available only on node `pcmk-1`, so that's the only node where the VM is capable of running. In a more realistic scenario, you'll probably want to have multiple nodes that are capable of running the VM.

Next we'll assign an attribute to node 1 that denotes its eligibility to host `vm-guest1`. If other nodes are capable of hosting your guest VM, then add the attribute to each of those nodes as well.

```
[root@pcmk-1 ~]# pcs node attribute pcmk-1 can-host-vm-guest1=1
```

Then we'll create a `VirtualDomain` resource so that Pacemaker can manage `vm-guest1`. Be sure to replace the XML file path below with your own if it differs. We'll also create a rule to prevent Pacemaker from trying to start the resource or probe its status on any node that isn't capable of running the VM. We'll save the CIB to a file, make both of these edits, and push them simultaneously.

```
[root@pcmk-1 ~]# pcs cluster cib vm_cfg
[root@pcmk-1 ~]# pcs -f vm_cfg resource create vm-guest1 VirtualDomain \
  hypervisor="qemu:///system" config="/etc/libvirt/qemu/vm-guest1.xml"
Assumed agent name 'ocf:heartbeat:VirtualDomain' (deduced from 'VirtualDomain')
[root@pcmk-1 ~]# pcs -f vm_cfg constraint location vm-guest1 rule \
  resource-discovery=never score=-INFINITY can-host-vm-guest1 ne 1
[root@pcmk-1 ~]# pcs cluster cib-push --config vm_cfg --wait
```

---

**Note:** If all nodes in your cluster are capable of hosting the VM that you've created, then you can skip the `pcs node attribute` and `pcs constraint location` commands.

---

---

**Note:** The ID of the resource managing the virtual machine (`vm-guest1` in the above example) **must** be different from the virtual machine's node name (`guest1` in the above example). Pacemaker will create an implicit internal resource for the Pacemaker Remote connection to the guest. This implicit resource will be named with the value of the `VirtualDomain` resource's `remote-node` meta attribute, which will be set by `pcs` to the guest node's node name. Therefore, that value cannot be used as the name of any other resource.

---

Now we can confirm that the `VirtualDomain` resource is running on `pcmk-1`.

```
[root@pcmk-1 ~]# pcs resource status
* vm-guest1      (ocf:heartbeat:VirtualDomain):   Started pcmk-1
```

## Prepare pcsd

Now we need to prepare `pcsd` on the guest so that we can use `pcs` commands to communicate with it.

Start and enable the `pcsd` daemon on the guest.

```
[root@guest1 ~]# systemctl start pcsd
[root@guest1 ~]# systemctl enable pcsd
Created symlink /etc/systemd/system/multi-user.target.wants/pcsd.service → /usr/lib/systemd/
↳system/pcsd.service.
```

Next, set a password for the `hacluster` user on the guest.

```
[root@guest1 ~]# echo MyPassword | passwd --stdin hacluster
Changing password for user hacluster.
passwd: all authentication tokens updated successfully.
```

Now authenticate the existing cluster nodes to pcsd on the guest. The below command only needs to be run from one cluster node.

```
[root@pcmk-1 ~]# pcs host auth guest1 -u hacluster
Password:
guest1: Authorized
```

### Integrate Guest Node into Cluster

We're finally ready to integrate the VM into the cluster as a guest node. Run the following command, which will create a guest node from the `VirtualDomain` resource and take care of all the remaining steps. Note that the format is `pcs cluster node add-guest <guest_name> <vm_resource_name>`.

```
[root@pcmk-1 ~]# pcs cluster node add-guest guest1 vm-guest1
No addresses specified for host 'guest1', using 'guest1'
Sending 'pacemaker authkey' to 'guest1'
guest1: successful distribution of the file 'pacemaker authkey'
Requesting 'pacemaker_remote enable', 'pacemaker_remote start' on 'guest1'
guest1: successful run of 'pacemaker_remote enable'
guest1: successful run of 'pacemaker_remote start'
```

You should soon see `guest1` appear in the `pcs status` output as a node. The output should look something like this:

```
[root@pcmk-1 ~]# pcs status
Cluster name: mycluster
Cluster Summary:
 * Stack: corosync
 * Current DC: pcmk-1 (version 2.1.2-4.el9-ada5c3b36e2) - partition with quorum
 * Last updated: Wed Aug 10 00:08:58 2022
 * Last change: Wed Aug 10 00:02:37 2022 by root via cibadmin on pcmk-1
 * 3 nodes configured
 * 3 resource instances configured

Node List:
 * Online: [ pcmk-1 pcmk-2 ]
 * GuestOnline: [ guest1@pcmk-1 ]

Full List of Resources:
 * xvm      (stonith:fence_xvm):      Started pcmk-1
 * vm-guest1 (ocf:heartbeat:VirtualDomain): Started pcmk-1

Daemon Status:
 corosync: active/disabled
 pacemaker: active/disabled
 pcsd: active/enabled
```

The resulting configuration should look something like the following:

```
[root@pcmk-1 ~]# pcs resource config
Resource: vm-guest1 (class=ocf provider=heartbeat type=VirtualDomain)
```

(continues on next page)

(continued from previous page)

```

Attributes: config=/etc/libvirt/qemu/vm-guest1.xml hypervisor=qemu:///system
Meta Attrs: remote-addr=guest1 remote-node=guest1
Operations: migrate_from interval=0s timeout=60s (vm-guest1-migrate_from-interval-0s)
            migrate_to interval=0s timeout=120s (vm-guest1-migrate_to-interval-0s)
            monitor interval=10s timeout=30s (vm-guest1-monitor-interval-10s)
            start interval=0s timeout=90s (vm-guest1-start-interval-0s)
            stop interval=0s timeout=90s (vm-guest1-stop-interval-0s)

```

## How pcs Configures the Guest

Let's take a closer look at what the `pcs cluster node add-guest` command is doing. There is no need to run any of the commands in this section.

First, `pcs` copies the Pacemaker authkey file to the VM that will become the guest. If an authkey is not already present on the cluster nodes, this command creates one and distributes it to the existing nodes and to the guest.

If you want to do this manually, you can run a command like the following to generate an authkey in `/etc/pacemaker/authkey`, and then distribute the key to the rest of the nodes and to the new guest.

```
[root@pcmk-1 ~]# dd if=/dev/urandom of=/etc/pacemaker/authkey bs=4096 count=1
```

Then `pcs` starts and enables the `pacemaker_remote` service on the guest. If you want to do this manually, run the following commands.

```
[root@guest1 ~]# systemctl start pacemaker_remote
[root@guest1 ~]# systemctl enable pacemaker_remote
```

Finally, `pcs` creates a guest node from the `VirtualDomain` resource by adding `remote-addr` and `remote-node` meta attributes to the resource. If you want to do this manually, you can run the following command if you're using `pcs`. Alternatively, run an equivalent command if you're using another cluster shell, or edit the CIB manually.

```
[root@pcmk-1 ~]# pcs resource update vm-guest1 meta remote-addr='guest1' \
remote-node='guest1' --force
```

### 2.3.4 Starting Resources on KVM Guest

The following example demonstrates that resources can be run on the guest node in the exact same way as on the cluster nodes.

Create a few `Dummy` resources. A `Dummy` resource is a real resource that actually executes operations on its assigned node. However, these operations are trivial (creating, deleting, or checking the existence of an empty or small file), so `Dummy` resources are ideal for testing purposes. `Dummy` resources use the `ocf:heartbeat:Dummy` or `ocf:pacemaker:Dummy` resource agent.

```
# for i in {1..5}; do pcs resource create FAKE${i} ocf:heartbeat:Dummy; done
```

Now run `pcs resource status`. You should see something like the following, where some of the resources are started on the cluster nodes, and some are started on the guest node.

```
[root@pcmk-1 ~]# pcs resource status
* vm-guest1      (ocf:heartbeat:VirtualDomain):  Started pcmk-1
* FAKE1         (ocf:heartbeat:Dummy):          Started guest1
* FAKE2         (ocf:heartbeat:Dummy):          Started pcmk-2
* FAKE3         (ocf:heartbeat:Dummy):          Started guest1
* FAKE4         (ocf:heartbeat:Dummy):          Started pcmk-2
* FAKE5         (ocf:heartbeat:Dummy):          Started guest1
```

The guest node, `guest1`, behaves just like any other node in the cluster with respect to resources. For example, choose a resource that is running on one of your cluster nodes. We'll choose `FAKE2` from the output above. It's currently running on `pcmk-2`. We can force `FAKE2` to run on `guest1` in the exact same way as we could force it to run on any particular cluster node. We do this by creating a location constraint:

```
# pcs constraint location FAKE2 prefers guest1
```

Now the `pcs resource status` output shows that `FAKE2` is on `guest1`.

```
[root@pcmk-1 ~]# pcs resource status
* vm-guest1      (ocf:heartbeat:VirtualDomain):  Started pcmk-1
* FAKE1         (ocf:heartbeat:Dummy):          Started guest1
* FAKE2         (ocf:heartbeat:Dummy):          Started guest1
* FAKE3         (ocf:heartbeat:Dummy):          Started guest1
* FAKE4         (ocf:heartbeat:Dummy):          Started pcmk-2
* FAKE5         (ocf:heartbeat:Dummy):          Started guest1
```

### 2.3.5 Testing Recovery and Fencing

Pacemaker's scheduler is smart enough to know fencing guest nodes associated with a virtual machine means shutting off/rebooting the virtual machine. No special configuration is necessary to make this happen. If you are interested in testing this functionality out, trying stopping the guest's `pacemaker_remote` daemon. This would be equivalent of abruptly terminating a cluster node's `corosync` membership without properly shutting it down.

ssh into the guest and run this command.

```
[root@guest1 ~]# kill -9 $(pidof pacemaker-remoted)
```

Within a few seconds, your `pcs status` output will show a monitor failure, and the `guest1` node will not be shown while it is being recovered.

```
[root@pcmk-1 ~]# pcs status
Cluster name: mycluster
Cluster Summary:
* Stack: corosync
* Current DC: pcmk-1 (version 2.1.2-4.el9-ada5c3b36e2) - partition with quorum
* Last updated: Wed Aug 10 01:39:40 2022
* Last change: Wed Aug 10 01:34:55 2022 by root via cibadmin on pcmk-1
* 3 nodes configured
* 8 resource instances configured

Node List:
* Online: [ pcmk-1 pcmk-2 ]

Full List of Resources:
* xvm      (stonith:fence_xvm):      Started pcmk-1
```

(continues on next page)

(continued from previous page)

```

* vm-guest1      (ocf:heartbeat:VirtualDomain):  FAILED pcmk-1
* FAKE1   (ocf:heartbeat:Dummy):    FAILED guest1
* FAKE2   (ocf:heartbeat:Dummy):    FAILED guest1
* FAKE3   (ocf:heartbeat:Dummy):    FAILED guest1
* FAKE4   (ocf:heartbeat:Dummy):    Started pcmk-2
* FAKE5   (ocf:heartbeat:Dummy):    FAILED guest1

Failed Resource Actions:
* guest1 30s-interval monitor on pcmk-1 could not be executed (Error) because 'Lost connection
↳to remote executor' at Wed Aug 10 01:39:38 2022

Daemon Status:
corosync: active/disabled
pacemaker: active/disabled
pcsd: active/enabled

```

**Note:** A guest node involves two resources: an explicitly configured resource that you create, which manages the virtual machine (the `VirtualDomain` resource in our example); and an implicit resource that Pacemaker creates, which manages the `pacemaker-remoted` connection to the guest. The implicit resource's name is the value of the explicit resource's `remote-node` meta attribute. When we killed `pacemaker-remoted`, the **implicit** resource is what failed. That's why the failed action starts with `guest1` and not `vm-guest1`.

Once recovery of the guest is complete, you'll see it automatically get re-integrated into the cluster. The final `pcs status` output should look something like this.

```

[root@pcmk-1 ~]# pcs status
Cluster name: mycluster
Cluster Summary:
* Stack: corosync
* Current DC: pcmk-1 (version 2.1.2-4.e19-ada5c3b36e2) - partition with quorum
* Last updated: Wed Aug 10 01:40:05 2022
* Last change: Wed Aug 10 01:34:55 2022 by root via cibadmin on pcmk-1
* 3 nodes configured
* 8 resource instances configured

Node List:
* Online: [ pcmk-1 pcmk-2 ]
* GuestOnline: [ guest1@pcmk-1 ]

Full List of Resources:
* xvm      (stonith:fence_xvm):    Started pcmk-1
* vm-guest1 (ocf:heartbeat:VirtualDomain): Started pcmk-1
* FAKE1   (ocf:heartbeat:Dummy):    Started guest1
* FAKE2   (ocf:heartbeat:Dummy):    Started guest1
* FAKE3   (ocf:heartbeat:Dummy):    Started pcmk-2
* FAKE4   (ocf:heartbeat:Dummy):    Started pcmk-2
* FAKE5   (ocf:heartbeat:Dummy):    Started guest1

Failed Resource Actions:
* guest1 30s-interval monitor on pcmk-1 could not be executed (Error) because 'Lost connection
↳to remote executor' at Wed Aug 10 01:39:38 2022

Daemon Status:
corosync: active/disabled

```

(continues on next page)

(continued from previous page)

```
pacemaker: active/disabled
pcsd: active/enabled
```

Normally, once you've investigated and addressed a failed action, you can clear the failure. However Pacemaker does not yet support cleanup for the implicitly created connection resource while the explicit resource is active. If you want to clear the failed action from the status output, stop the guest resource before clearing it. For example:

```
# pcs resource disable vm-guest1 --wait
# pcs resource cleanup guest1
# pcs resource enable vm-guest1
```

### 2.3.6 Accessing Cluster Tools from Guest Node

Besides allowing the cluster to manage resources on a guest node, `pacemaker_remote` has one other trick. The `pacemaker_remote` daemon allows nearly all the pacemaker tools (`crm_resource`, `crm_mon`, `crm_attribute`, etc.) to work on guest nodes natively.

Try it: Run `crm_mon` on the guest after pacemaker has integrated the guest node into the cluster. These tools just work. This means resource agents such as promotable resources (which need access to tools like `crm_attribute`) work seamlessly on the guest nodes.

Higher-level command shells such as `pcs` may have partial support on guest nodes, but it is recommended to run them from a cluster node.

### 2.3.7 Troubleshooting a Remote Connection

If connectivity issues occur, it's worth verifying that the cluster nodes can communicate with the guest node on TCP port 3121. We can use the `nc` command to test the connection.

On the cluster nodes, install the package that provides the `nc` command. The package name may vary by distribution; on AlmaLinux 9 it's `nmap-ncat`.

Now connect using `nc` from each of the cluster nodes to the guest and run a `/bin/true` command that does nothing except return success. No output indicates that the cluster node is able to communicate with the guest on TCP port 3121. An error indicates that the connection failed. This could be due to a network issue or because `pacemaker-remoted` is not currently running on the guest node.

Example of success:

```
[root@pcmk-1 ~]# nc guest1 3121 --sh-exec /bin/true
[root@pcmk-1 ~]#
```

Examples of failure:

```
[root@pcmk-1 ~]# nc guest1 3121 --sh-exec /bin/true
Ncat: Connection refused.
[root@pcmk-1 ~]# nc guest1 3121 --sh-exec /bin/true
Ncat: No route to host.
```

## 2.4 Remote Node Walk-through

**What this tutorial is:** An in-depth walk-through of how to get Pacemaker to integrate a remote node into the cluster as a node capable of running cluster resources.

**What this tutorial is not:** A realistic deployment scenario. The steps shown here are meant to get users familiar with the concept of remote nodes as quickly as possible.

### 2.4.1 Configure Cluster Nodes

This walk-through assumes you already have a Pacemaker cluster configured. For examples, we will use a cluster with two cluster nodes named `pcmk-1` and `pcmk-2`. You can substitute whatever your node names are, for however many nodes you have. If you are not familiar with setting up basic Pacemaker clusters, follow the walk-through in the Clusters From Scratch document before attempting this one.

### 2.4.2 Configure Remote Node

#### Configure Firewall on Remote Node

Allow cluster-related services through the local firewall:

```
# firewall-cmd --permanent --add-service=high-availability
success
# firewall-cmd --reload
success
```

---

**Note:** If you are using some other firewall solution besides `firewalld`, simply open the following ports, which can be used by various clustering components: TCP ports 2224, 3121, and 21064.

If you run into any problems during testing, you might want to disable the firewall and SELinux entirely until you have everything working. This may create significant security issues and should not be performed on machines that will be exposed to the outside world, but may be appropriate during development and testing on a protected host.

To disable security measures:

```
# setenforce 0
# sed -i.bak "s/SELINUX=enforcing/SELINUX=permissive/g" \
  /etc/selinux/config
# systemctl mask firewalld.service
# systemctl stop firewalld.service
```

#### Configure `/etc/hosts`

You will need to add the remote node's hostname (we're using `remotel` in this tutorial) to the cluster nodes' `/etc/hosts` files if you haven't already. This is required unless you have DNS set up in a way where `remotel`'s address can be discovered.

For each remote node, execute the following on each cluster node and on the remote nodes, replacing the IP address with the actual IP address of the remote node.



```
# cat << END >> /etc/hosts
192.168.122.10  remotel
END
```

Also add entries for each cluster node to the `/etc/hosts` file on each remote node. For example:

```
# cat << END >> /etc/hosts
192.168.122.101  pcmk-1
192.168.122.102  pcmk-2
END
```

## Configure `pacemaker_remote` on Remote Node

Install the `pacemaker_remote` daemon on the remote node.

```
[root@remotel ~]# dnf config-manager --set-enabled highavailability
[root@remotel ~]# dnf install -y pacemaker-remote resource-agents pcs
```

## Prepare `pcsd`

Now we need to prepare `pcsd` on the remote node so that we can use `pcs` commands to communicate with it.

Start and enable the `pcsd` daemon on the remote node.

```
[root@remotel ~]# systemctl start pcsd
[root@remotel ~]# systemctl enable pcsd
Created symlink /etc/systemd/system/multi-user.target.wants/pcsd.service → /usr/lib/systemd/
system/pcsd.service.
```

Next, set a password for the `hacluster` user on the remote node

```
[root@remotel ~]# echo MyPassword | passwd --stdin hacluster
Changing password for user hacluster.
passwd: all authentication tokens updated successfully.
```

Now authenticate the existing cluster nodes to `pcsd` on the remote node. The below command only needs to be run from one cluster node.

```
[root@pcmk-1 ~]# pcs host auth remotel -u hacluster
Password:
remotel: Authorized
```

## Integrate Remote Node into Cluster

Integrating a remote node into the cluster is achieved through the creation of a remote node connection resource. The remote node connection resource both establishes the connection to the remote node and defines that the remote node exists. Note that this resource is actually internal to Pacemaker's controller. The metadata for this resource can be found in the `/usr/lib/ocf/resource.d/pacemaker/remotel` file. The metadata in this file describes what options are available, but there is no actual `ocf:pacemaker:remotel` resource agent script that performs any work.

Define the remote node connection resource to our remote node, `remotel`, using the following command on any cluster node. This command creates the `ocf:pacemaker:remotel` resource; creates the authkey if it does

not exist already and distributes it to the remote node; and starts and enables `pacemaker-remoted` on the remote node.

```
[root@pcmk-1 ~]# pcs cluster node add-remote remotel
No addresses specified for host 'remotel', using 'remotel'
Sending 'pacemaker authkey' to 'remotel'
remotel: successful distribution of the file 'pacemaker authkey'
Requesting 'pacemaker_remote enable', 'pacemaker_remote start' on 'remotel'
remotel: successful run of 'pacemaker_remote enable'
remotel: successful run of 'pacemaker_remote start'
```

That's it. After a moment you should see the remote node come online. The final `pcs status` output should look something like this, and you can see that it created the `ocf:pacemaker:remote` resource:

```
[root@pcmk-1 ~]# pcs status
Cluster name: mycluster
Cluster Summary:
 * Stack: corosync
 * Current DC: pcmk-1 (version 2.1.2-4.el9-ada5c3b36e2) - partition with quorum
 * Last updated: Wed Aug 10 05:17:28 2022
 * Last change: Wed Aug 10 05:17:26 2022 by root via cibadmin on pcmk-1
 * 3 nodes configured
 * 2 resource instances configured

Node List:
 * Online: [ pcmk-1 pcmk-2 ]
 * RemoteOnline: [ remotel ]

Full List of Resources:
 * xvm      (stonith:fence_xvm):      Started pcmk-1
 * remotel (ocf:pacemaker:remote):  Started pcmk-1

Daemon Status:
 corosync: active/disabled
 pacemaker: active/disabled
 pcsd: active/enabled
```

### 2.4.3 How pcs Configures the Remote

Let's take a closer look at what the `pcs cluster node add-remote` command is doing. There is no need to run any of the commands in this section.

First, `pcs` copies the Pacemaker authkey file to the VM that will become the guest. If an authkey is not already present on the cluster nodes, this command creates one and distributes it to the existing nodes and to the guest.

If you want to do this manually, you can run a command like the following to generate an authkey in `/etc/pacemaker/authkey`, and then distribute the key to the rest of the nodes and to the new guest.

```
[root@pcmk-1 ~]# dd if=/dev/urandom of=/etc/pacemaker/authkey bs=4096 count=1
```

Then `pcs` starts and enables the `pacemaker_remote` service on the guest. If you want to do this manually, run the following commands.

```
[root@guest1 ~]# systemctl start pacemaker_remote
[root@guest1 ~]# systemctl enable pacemaker_remote
```

## 2.4.4 Starting Resources on Remote Node

Once the remote node is integrated into the cluster, starting and managing resources on a remote node is the exact same as on cluster nodes. Refer to the [Clusters from Scratch](#) document for examples of resource creation.

**Warning:** Never involve a remote node connection resource in a resource group, colocation constraint, or order constraint.

## 2.4.5 Fencing Remote Nodes

Remote nodes are fenced the same way as cluster nodes. No special considerations are required. Configure fencing resources for use with remote nodes the same as you would with cluster nodes.

Note, however, that remote nodes can never ‘initiate’ a fencing action. Only cluster nodes are capable of actually executing a fencing operation against another node.

## 2.4.6 Accessing Cluster Tools from a Remote Node

Besides allowing the cluster to manage resources on a remote node, `pacemaker_remote` has one other trick. The `pacemaker_remote` daemon allows nearly all the `pacemaker` tools (`crm_resource`, `crm_mon`, `crm_attribute`, etc.) to work on remote nodes natively.

Try it: Run `crm_mon` on the remote node after `pacemaker` has integrated it into the cluster. These tools just work. These means resource agents such as promotable resources (which need access to tools like `crm_attribute`) work seamlessly on the remote nodes.

Higher-level command shells such as `pcs` may have partial support on remote nodes, but it is recommended to run them from a cluster node.

## 2.4.7 Troubleshooting a Remote Connection

If connectivity issues occur, it’s worth verifying that the cluster nodes can communicate with the remote node on TCP port 3121. We can use the `nc` command to test the connection.

On the cluster nodes, install the package that provides the `nc` command. The package name may vary by distribution; on AlmaLinux 9 it’s `nmap-ncat`.

Now connect using `nc` from each of the cluster nodes to the remote node and run a `/bin/true` command that does nothing except return success. No output indicates that the cluster node is able to communicate with the remote node on TCP port 3121. An error indicates that the connection failed. This could be due to a network issue or because `pacemaker-remoted` is not currently running on the remote node.

Example of success:

```
[root@pcmk-1 ~]# nc remote1 3121 --sh-exec /bin/true
[root@pcmk-1 ~]#
```

Examples of failure:

```
[root@pcmk-1 ~]# nc remote1 3121 --sh-exec /bin/true
Ncat: Connection refused.
[root@pcmk-1 ~]# nc remote1 3121 --sh-exec /bin/true
Ncat: No route to host.
```

## 2.5 Alternative Configurations

These alternative configurations may be appropriate in limited cases, such as a test cluster, but are not the best method in most situations. They are presented here for completeness and as an example of Pacemaker's flexibility to suit your needs.

### 2.5.1 Virtual Machines as Cluster Nodes

The preferred use of virtual machines in a Pacemaker cluster is as a cluster resource, whether opaque or as a guest node. However, it is possible to run the full cluster stack on a virtual node instead.

This is commonly used to set up test environments; a single physical host (that does not participate in the cluster) runs two or more virtual machines, all running the full cluster stack. This can be used to simulate a larger cluster for testing purposes.

In a production environment, fencing becomes more complicated, especially if the underlying hosts run any services besides the clustered VMs. If the VMs are not guaranteed a minimum amount of host resources, CPU and I/O contention can cause timing issues for cluster components.

Another situation where this approach is sometimes used is when the cluster owner leases the VMs from a provider and does not have direct access to the underlying host. The main concerns in this case are proper fencing (usually via a custom resource agent that communicates with the provider's APIs) and maintaining a static IP address between reboots, as well as resource contention issues.

### 2.5.2 Virtual Machines as Remote Nodes

Virtual machines may be configured following the process for remote nodes rather than guest nodes (i.e., using an **ocf:pacemaker:remote** resource rather than letting the cluster manage the VM directly).

This is mainly useful in testing, to use a single physical host to simulate a larger cluster involving remote nodes. Pacemaker's Cluster Test Suite (CTS) uses this approach to test remote node functionality.

### 2.5.3 Containers as Guest Nodes

[Containers](#) and in particular Linux containers (LXC) and Docker, have become a popular method of isolating services in a resource-efficient manner.

The preferred means of integrating containers into Pacemaker is as a cluster resource, whether opaque or using Pacemaker's **bundle** resource type.

However, it is possible to run `pacemaker_remote` inside a container, following the process for guest nodes. This is not recommended but can be useful, for example, in testing scenarios, to simulate a large number of guest nodes.

The configuration process is very similar to that described for guest nodes using virtual machines. Key differences:

- The underlying host must install the libvirt driver for the desired container technology – for example, the `libvirt-daemon-lxc` package to get the `libvirt-lxc` driver for LXC containers.
- Libvirt XML definitions must be generated for the containers. You can create XML definitions manually, following the appropriate libvirt driver documentation.
- To share the authentication key, either share the host's `/etc/pacemaker` directory with the container, or copy the key into the container's filesystem.
- The **VirtualDomain** resource for a container will need `force_stop="true"` and an appropriate hypervisor option, for example `hypervisor="lxc:///"` for LXC containers.



**INDEX**

- genindex
- search





## INDEX

### B

bundle, 24

### C

cluster node, 5

configuration, 8

    guest node, 8

    remote node, 9

container

    as guest node, 24

    bundle, 24

    Docker, 24

    LXC, 24

### D

Docker, 24

### G

guest node, 5

    configuration, 8

    firewall, 12

    meta-attribute, 8

    walk-through, 11

### L

LXC, 24

### N

node

    cluster node, 5

    guest node, 5

    remote node, 5

### P

pacemaker-remoted, 5

### R

remote node, 5

    configuration, 9

    fencing, 23

    firewall, 20

    walk-through, 19

### V

virtual machine

    as cluster node, 24

    as guest node, 6

    as remote node, 24